

MicroStation V8i Installation Instructions.

Version 08.11.09.919

1. Installing MicroStation V8i SS10. Download installation package from <ftp://dpwftp.co.la.ca.us/pub/ITD Bentley Support/Software/MicroStation V8i SS10/ms081109919en.exe>
2. Run the *ms081109919en.exe* file.
 - a. If .NET 3.5 Framework is required, go to Control Panel > Windows Features > Turn Windows features on or off > to enable.




- b. At the first install dialog box (there will be a total of three), select **Extract & Install Installation Package**.
- c. Accept the default path for **Extract to this Folder**. Click **OK**.
- d. The second dialog of the installer will show the status of the items that will be installed. Click **Install**.
- e. At the **Welcome to . . . Setup Wizard** dialog click **Next**.
- f. A third installer dialog will open. After “computing space requirements:”
 - i. Click Next.
 - ii. Accept the terms of the License Agreement. Click Next.
 - iii. Destination Folder. Accept the default locations. Click Next.
 - iv. Configure Shortcuts. Select the **Start Menu** and **Desktop** boxes. Click Next.
 - v. Choose Setup Type. Click on **Typical**.
 - vi. Ready to Install MicroStation V8i. Click **Install**.

- g. Return to the second Install dialog box. When all items show status of *Installed* (and a green checkmark), click **Finish**.
3. Download CADD Standards <http://dpw.lacounty.gov/nas/gis/cad/standards/V8i-WorkSpace.zip>
4. Unzip the **v8i-Workspace.zip** file. Zip file may be in your Downloads folder.

Note: This next step will wipe out the existing workspace! If in doubt, backup folder beforehand

5. Delete the contents in *C:\ProgramData\Bentley\MicroStation V8i (SELECTseries)\Workspace* (If you cannot see the *ProgramData* folder, click on **View** in file Explorer and enable “Hidden Items”)
6. Copy these folders from the zip file:
 - Interfaces
 - Projects
 - Standards
 - System
 - Users
7. Paste to root of *C:\ProgramData\Bentley\MicroStation V8i (SELECTseries)\Workspace*
8. Go to the *C:\ProgramData\Microsoft\Windows\Start Menu\Programs\Bentley\MicroStation V8i (SELECTseries 10)* folder and delete the following shortcut:
 - a. MicroStation V8i (Select Series 10) (High Security)
9. Create this folder *C:\MyFiles* if it doesn't already exist. This will be the default output location for print jobs to PDF, saved files, etc.
10. Log in to the Bentley CONNECTIONclient.
11. Launch MicroStation. Change the following settings: Workspace > Preferences > Raster Manager > Georeference > Default Unit Settings > US Survey Feet



12. Go to: File > Save Settings.

13. This completes the installation of **MicroStation V8i (SelectSeries 10)**